

Secure Remote Access (SRA) | Remote Support

Remote Support: IT Admin Guide

Document Information

Code: **PM-SUP-ITAG**

Version: **1.1**

Date: **4 October 2024**


Copyright © 2024 Admin By Request

All rights reserved.

Information in this document is subject to change without notice. The software described in this document is furnished under a license agreement or nondisclosure agreement (NDA). The software may be used or copied only in accordance with the terms of those agreements.

No part of this publication may be reproduced, stored in a retrieval system, or transmitted in any form or any means electronic or mechanical, including photocopying and recording for any purpose other than the customer's stated use without the written permission of Admin By Request.

Contact Admin By Request

 +64 21 023 57020

 marketing@adminbyrequest.com

 adminbyrequest.com

 Unit C, 21-23 Elliot St, Papakura

Table of Contents

Remote Support Overview	1
What is Remote Support?	1
Prerequisites	1
How does Remote Support work?	2
End user initiated	2
IT admin initiated	2
Product Enrollment	3
What is Product Enrollment?	3
How does it work?	3
Getting started with Product Enrollment	3
Platform Scope	4
Licensing overview	5
Test Drive	5
Scope by computer groups	5
Scope by manual selection	5
Getting Started with Remote Support	7
How do I get started?	7
Requesting Remote Support (end user initiated)	8
Starting Remote Support (IT admin initiated)	9
Ending the session	10
What next?	11
Basic Settings for Remote Support	12
Set desktop icon	12
Enable session recording	13
Require Multi-Factor Authentication	14
Specify View Only for portal admin	15
Set session expiry	15
Portal Administration for Remote Support	16
Introduction	16
In this topic	16
Remote Support Settings	17
Authorization	17
Endpoint	18
Settings	18

Security	19
Emails	20
Sub Settings	24
Overruling a global setting	24
Scope for sub-settings	25
About sub-settings scope	26
Document History	27
Index	28

Remote Support Overview

What is Remote Support?

Remote Support is part of the Secure Remote Access product by Admin By Request, that allows you to share screens and remotely control devices inside of your Admin By Request inventory, while using all of the well-known features of the Admin By Request ecosystem, such as: inventory, auditlog, settings and sub-settings, approval flows etc.

Remote Support allows either end users or IT admins to initiate a secure, just-in-time, remote support session – allowing them to share and control the end-user's device – and tear everything down once the session is done – eliminating any access points for bad actors.

This document covers getting started with Product Enrollment and Remote Support. It also describes key settings that can be administered from the portal.

Prerequisites

In order to use the full power of Remote Support, there are a number of requirements:

- Access to the portal at **<https://www.adminbyrequest.com/Login>**
 - Admin By Request for **Windows 8.4.0, Build 31936+** on each client
 - Admin By Request API - port **443** for the following:
 - **api1.adminbyrequest.com** (if your data is located in Europe)
 - **api2.adminbyrequest.com** (if your data is located in the USA)
 - **api.adminbyrequest.com**
 - Outbound MQTT broker connectivity via Websockets- port **443** for the following:
 - **FastTrackHubEU1.azure-devices.net** (if your data is located in Europe)
 - **FastTrackHubUS1.azure-devices.net** (if your data is located in the USA)
 - Cloudflare connectivity:
 - UDP outbound - port **7844** for the following:
 - **region1.v2.argotunnel.com**
 - **region2.v2.argotunnel.com**
 - If your firewall supports Server Name Indication (SNI), you need to allow the following URLs (UDP outbound - port **7844**):
 - **cftunnel.com**
 - **h2.cftunnel.com**
 - **quic.cftunnel.com**
- Refer to <https://developers.cloudflare.com/cloudflare-one/connections/connect-networks/deploy-tunnels/tunnel-with-firewall/> for more information on Cloudflare's "tunnel with firewall" configuration.
- The endpoint needs to be enrolled with an Admin By Request Secure Remote Access license (see "[Product Enrollment](#)" on page 3).


How does Remote Support work?

Remote Support is based on the same gateway concept as the Unattended Access gateway, which is also part of the Admin By Request Secure Remote Access product. It allows a just-in-time setup between the gateway and the endpoint by establishing a secure Cloudflare tunnel.

Once the tunnel is established, a just-in-time server session is created on the endpoint – allowing for screen sharing and remote control via the browser.

Once the session is terminated or expires, the tunnel and the server session are terminated, leaving the endpoint in the same state as before the remote support session.

The setup is fully cloud-based and does not require any on-premise setup besides what's mentioned in the prerequisites:



The flow for a Remote Support session can be initiated either by an end user or by an IT administrator via the portal .

End user initiated

- The end user requests a Remote Support session from their endpoint – providing a reason for the request.
- The IT admin approves (or denies) the request via the Admin By Request portal.

IT admin initiated

- The IT admin navigates to a specific device in the Admin By Request portal inventory and clicks **Support** on the relevant endpoint to initiate a remote support session.
- The end user is asked to approve the incoming Remote Support session from the IT admin.
- Upon approval, a secure Cloudflare tunnel is initiated between the Admin By Request gateway and the endpoint and a just-in-time server session is created on the endpoint.
- The IT admin is now connected to the endpoint via the secure tunnel and the remote support session commences.

Once the session is terminated – or expires – the session server and the tunnel are terminated.

The session is logged in the audit log in the Admin By Request portal, allowing for the IT admin to access documentation about each remote support session – as well as download a recording of each session (if recording is enabled).

Based on the settings, each Remote Support session can be adapted with various security and compliance features like: Multi-Factor Authentication (MFA), view-only access, session expiration and session recording.

Product Enrollment

What is Product Enrollment?

Product enrollment is the mechanism of determining which Admin By Request licenses – and hence product capabilities – should be available to specific endpoints.

How does it work?

In a real-world scenario, a company might have 100 endpoints and the following Admin By Request licenses:


- 100 Endpoint Privilege Management (EPM) licenses
- 50 Secure Remote Access (SRA) licenses

Product enrollment allows the customer to determine which endpoints are activated with an EPM license, an SRA license – or both.

Once an endpoint gets a specific license, the corresponding functionality is instantly available on that endpoint. For example, if an endpoint gets a Secure Remote Access license then this device can now use both [Unattended Access](#) and [Remote Support](#).


Getting started with Product Enrollment

All product enrollment takes place from the Product Enrollment menu in the portal (**Settings > Product Enrollment**):



This menu is available from both EPM and SRA views.

The Product Enrollment page provides a way to assign licenses for specific Admin By Request products. The specific product is selected via tabs at the top – currently **ENDPOINT PRIVILEGE MANAGEMENT** and **SECURE REMOTE ACCESS** are available:




From each product tab, it's possible to determine the scope of enrollment for that product, as well as get an overview of the current license usage based on the selection.

Platform Scope

The Platform Scope allows for quickly setting up which inventory groups should have the current product license assigned.

In the following example, the tenant is set up to have all Windows Workstations and Windows Servers enrolled with the Endpoint Privilege Management product – while Apple Macs and Linux devices won't be able to utilize the EPM functionality:



Licensing overview

The license overview box shows how many licenses are actually used by the current enrollment settings – and how many licenses are left in the pool of purchased licenses.


In the example above, the tenant has 100 licenses for both Workstation and Server – and the current selected enrollment uses 2 Workstation licenses and 1 Server license – leaving the tenant with a buffer of 98 for Workstation and 99 for Server Edition.

Test Drive

The Test Drive mode allows a portal user to cherry pick which devices are enrolled with the selected product. This can either be done by specifying a computer group scope or by manually picking devices.

Scope by computer groups


To apply the scope only to devices within specific computer groups, enter the group names into the "Computer groups" box:




In this example, the enrollment will affect only devices in the group "TestDevices".

Scope by manual selection

To manually pick which devices should be enrolled, the Test Drive switch can be turned **On**:




The **Pick computers** button is now available and allows for manual selection of the devices to enroll into the selected product:



In this example, the device named **VM2022TEST** has been enrolled with Endpoint Privilege Management, while the devices on the left have not.

To enroll devices, click the **Enroll >>** button for the specific device. To remove a device, click the **<< Remove** button for the device.

Going back to the enrollment page now shows the following license usage for the tenant:



Allowing for test driving Endpoint Privilege Management for the single selected device.

Please be aware that turning test drive on or off will cause licenses to be removed from non-selected devices. Only use the test drive feature if you manually want to pick the devices to enroll.

Getting Started with Remote Support


How do I get started?

In order to access a device using Remote Support, the device needs to be enrolled with the Admin By Request Secure Remote Access product (see "[Product Enrollment](#)" on page 3).


After the device is enrolled, the settings scope needs to allow Remote Support sessions.

To allow Remote Support sessions:

1. Navigate to the Admin By Request portal
2. Ensure that the **Secure Remote Access** view is selected either on the *Summary* page or via the product selector in the menu:



3. From the Settings menu, select **Remote Support Settings**.
4. Under the **AUTHORIZATION** tab, ensure that "Allow Remote Support" is set to **On**:




This ensures that devices falling within this settings scope have the ability to request a Remote Support session (or have one requested by a portal user).


Requesting Remote Support (end user initiated)

To request a Remote Support session as an end user, the end user does the following:


1. From the endpoint with the Admin By Request client installed, navigate to the Admin By Request tray icon (or use the desktop icon if this has been enabled - see "Set desktop icon" on page 12).
2. Right-click the icon and select the **Remote Support** item:




3. This prompts the user for contact information as well as a reason for the Remote Support request:



4. All Remote Support requests awaiting approval can be found by the portal admin in the Admin By Request portal under "Requests" with the "Secure Remote Access" view selected in the product selector:



- The portal admin can now approve or deny the request. If the request is approved, the end user is prompted to allow the connection:




- By clicking **Yes**, the secure tunnel and just-in-time server session is initialized, and the portal user is now connected to a Remote Support session – sharing the screen and input (if enabled - see "Specify View Only for portal admin" on page 15) directly in the browser.


Starting Remote Support (IT admin initiated)

To start a Remote Support session as a portal administrator, the following sequence occurs:


- The portal admin identifies the target device in the Inventory and then either:
 - clicks **Support** from the Inventory list:



- or, clicks the **Screenshare** button in the Remote Support panel (after drilling down into inventory details for the endpoint):



- After either is clicked, the end-user receives a pop-up asking to accept the incoming connection:




- If the end user clicks **Yes**, the secure tunnel and just-in-time server session is initialized, and the portal admin is now connected to a Remote Support session – sharing the screen and input (if enabled - see "[Specify View Only for portal admin](#)" on page 15) directly in the browser.
- If the end user clicks **No**, the portal admin request to start a Remote Support session is denied. In any case, all request details are logged in the Auditlog.

Ending the session

A Remote Support session can end in a number of ways:


- Either party can end the session by pressing the **Done** button in the pop-up:




- By pressing the **Off** icon in the action bar of the browser (IT admin only):



- If session expiration (see "[Set session expiry](#)" on page 15) is enabled, the session will be terminated after the set amount of time. When the remaining time gets below 2 minutes, a countdown appears:



- By pressing the **Terminate this session** from the auditlog details of an ongoing Remote Support session:



What next?

Check out "[Basic Settings for Remote Support](#)" on page 12 for details on how to setup the following:


- A desktop icon
- Session recordings
- MFA for extra security
- View-only for the portal admin
- Session expiry

Basic Settings for Remote Support

Set desktop icon

To create a desktop icon on devices that support Remote Support, navigate to the Remote Support Settings and select the "Endpoint" tab.

From here, the "Create desktop icon" setting can be enabled or disabled:



Enabling the setting will create a desktop icon on the affected devices with the supplied desktop icon name. If no name is supplied, a default localized name is used:




Note that a Tray Tool menu item is always created for Remote Support.

Refer to "[Endpoint](#)" on page 18 (ICON) for more information.


Enable session recording

Session recordings can be enabled or disabled from the "Settings" tab under the Remote Support Settings:



Enabling the session recordings creates a screen recording of all Remote Support sessions done under this setting scope.


Recordings can be requested via the auditlog after a session has ended by clicking the **Request this video** button under the auditlog entry:




Refer to "Settings" on page 18 (RECORDING) for more information.

Require Multi-Factor Authentication

Enabling the "Require MFA" setting will require the portal user to re-authenticate using MFA before being able to start any Remote Support session (both end-user and portal user initiated):



With MFA enabled, the portal user will be met with the Microsoft account login screen:



This is a required step before being able to proceed to initiating the Remote Support session with the endpoint.


NOTE:

Using the MFA setting requires the portal user to be signed into the portal using Microsoft SSO.

Refer to "[Security](#)" on [page 19](#) (MFA) for more information.

Specify View Only for portal admin

To have Remote Support sessions be view-only (meaning that the portal admin can only view the screen but not control mouse or keyboard), the **View Only** setting can be enabled:




Upon enabling this setting, all Remote Support session made from this setting scope will be screensharing only but with no control over mouse or keyboard. This is particularly useful when supporting sensitive endpoints like e.g. C-level devices.

Refer to "[Security](#)" on page 19 (VIEW ONLY) for more information.

Set session expiry

To prevent sessions from being "forgotten" and therefore run forever, the session expiry setting can be used:



By setting a session expiry setting, all Remote Support sessions that fall under this setting scope will automatically be disconnected after the selected amount of time has expired.

The connected users will get a countdown warning when the remaining time gets below 2 minutes.

To disable session expiration, select "Unlimited" as the expiration value.

Refer to "[Security](#)" on page 19 (SESSION EXPIRY) for more information.

Portal Administration for Remote Support

Introduction

This topic describes several key areas of the Admin Portal that can be used to manage *Remote Support Settings* and *Sub Settings*.

Fields that can be set and/or configured in the portal are presented in tables, with each table showing:

- **Setting** - the name of the field that controls the setting
- **Type** - the type of value that can be entered or selected and its default value
- **Description** - how the setting is used and notes about any implications it may have on other settings

To change any of the settings in the portal, [log in to the portal](#) and select the setting from the menu.

In this topic

["Remote Support Settings" on the next page](#)

["Authorization" on the next page](#)

["Endpoint" on page 18](#)

["Settings" on page 18](#)

["Security" on page 19](#)

["Emails" on page 20](#)

["Sub Settings" on page 24](#)

Remote Support Settings

Portal menu: **SRA > Settings > Remote Support Settings**

Settings here are the global settings for all endpoints participating in the feature. You can overrule settings for listed domain users or computers under the sub-settings menu.

Authorization

Portal menu: **SRA > Settings > Remote Support Settings > Authorization**

AUTHORIZATION tab

Remote Support allows users to remotely assist other users with issues. It is often combined with the EPM feature *Support Assist* to perform installs without logging the user out and without giving the user admin rights.

Remote Support requires Windows endpoint software **8.4+** and is part of the Secure Remote Access product suite.

Setting	Type	Description
Allow Remote Support	Toggle On Off Default: On	<p>On - Allows computers to be accessed remotely, provided a user is present (i.e. remote user must confirm). Note that supporting user might only be able to watch and not take control (see Security settings (VIEW ONLY tab))).</p> <p>Off - Computers cannot be accessed remotely regardless of whether a user is present or not. Note that <i>Unattended Access</i> might still be possible, depending on Unattended Access settings.</p>
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

NOTIFICATION tab

Email notification to administrators is available when *Require approval* is checked under Authorization.

Notifications can be sent for the following scenarios:

- Each new request for approval (*Run As Admin*) or admin session access (*Admin Session*)
- When malware is detected (Workstation Settings > [OS] Settings > Malware)
- When unattended remote access is requested (*Unattended Access*)
- When either an end user or portal admin initiates a *Remote Support* session.

As with other request types, new requests for approval always appear under **Requests > Pending** in the Portal top menu. This is the case for both Endpoint Privilege Management and Secure Remote Access.

The *Notification* setting enables and configures **additional email notification** for new requests. If multiple email addresses are specified, they must be on separate lines.

NOTE:

Phone notification is separate and happens automatically via push notifications to phones with the **mobile app** installed.

Setting	Type	Description
Send email notifications	Toggle On Off Default: Off	On - Additional email notifications are sent to the email addresses listed in <i>Email addresses</i> . Off - Email notifications are not sent.
Email addresses	Text	Standard email address format. Use a new line for each address.
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

Endpoint

Portal menu: **SRA > Settings > Remote Support Settings > Endpoint**

ICON tab

An icon for Remote Support appears in the system tray at install time.

This setting lets you optionally also place an icon on the user's desktop. If you enable the desktop icon, but do not specify a desktop icon name, the default "Administrator Access" text will be used in a localized version (English, German, French, Spanish, Danish, Swedish and Norwegian).

Setting	Type	Description
Create desktop icon	Toggle On Off Default: On	On - Place icon on the desktop. Off - Do not place icon on the desktop. Only the tray tool icon will be available.
Desktop icon name	Text	Label to use for the icon. If left blank, Administrator Access is used as the label.
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

Settings

Portal menu: **SRA > Settings > Remote Support Settings > Settings**

RECORDING tab

Screen recording means that the remote session is recorded.

Files are stored locally and can be requested in the auditlog by expanding the relevant line.

Setting	Type	Description
Screen recording	Toggle On Off Default: Off	On - Screen recording is enabled. Off - Screen recording is disabled.
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

Security

Portal menu: **SRA > Settings > Remote Support Settings > Security**

MFA tab

MFA (Multi-Factor Authentication) requires the portal user to re-authenticate with single sign-on when connecting remotely to an endpoint.

If the logged-on portal user does *not* log on with SSO (single sign-on), the user will be denied access to the endpoint.

Setting	Type	Description
Require MFA	Toggle On Off Default: On	On - The logged-on portal user must authenticate via SSO when connecting remotely to an endpoint. Off - Portal user does not need to authenticate via SSO to remotely connect.
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

VIEW tab

View Only means that the portal user can watch, but not interact with the endpoint.

This is useful for sensitive endpoints, such as c-level computers. You can create sub settings for sensitive computers based on computer groups.

Setting	Type	Description
Assist Only	Toggle On Off Default: On	On - The portal user can only watch, but not interact with the endpoint. Off - Portal user can take control of screen and keyboard during a session.
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

SESSION EXPIRY tab

Session expiry is the maximum length a remote session may last. When this time expires, the remote session will be disconnected.

NOTE:

Selecting **Unlimited** is not recommended, as this would result in no expiry on the remote session.

Setting	Type	Description
Session expiry	Selection Default: 4 hours	Select a value between 15 minutes and Unlimited . Custom is also available - if selected, choose the required number of Hours and Minutes .
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

Emails

Portal menu: **SRA > Settings > Remote Support Settings > Emails**

REQUEST EMAILS tab

Emails go out when *Require approval* is turned **On** under . You can create your own email templates here with information specific to your company, such as a Help Desk phone number and custom instructions.

Setting	Type	Description
Email template	Selection Default: Approved email	<p>Approved email - Loads a template that advises <i>the user</i> (i.e. requester) that the request for access has been approved.</p> <p>Denied email - Loads a template that advises the request for access has been denied without giving a reason.</p> <p>Denied with reason - Loads a template that advises the request for access has been denied and provides the reason.</p> <p>Administrator notify - Loads a template that advises <i>the administrator</i> (i.e. person who approves or denies) that a request for access is waiting for attention.</p>
Email sender	Text Default: Admin By Request Team	The email address to be used as the sender for the email. Can be used with custom domains. Use the Email address button to set up custom domains. Refer to Email Domain for more information on configuring an email address to be used as the sender for all user notifications.
Email subject	Text Default: Admin By Request	Text that will appear in the subject line of emails.

Setting	Type	Description
Get default	Button	<p>Loads the default <i>Email template</i> for the option selected.</p> <p>NOTE:</p> <ul style="list-style-type: none"> • Default email templates are created by Admin By Request. Contact us if you wish to customize a default email template. • Using this button will overwrite any customization you might have done in the <i>Template body</i>.
Email address	Button	<p>Switches to Email Domain in Tenant Settings in the portal, allowing you to use a custom domain as the sender.</p> <p>This allows sending email from domains other than @adminbyrequest.com.</p> <p>NOTE:</p> <p>This is optional, but you cannot add an email sender field of e.g. "tom@mydomain.com" <i>unless</i> you have first set up the custom email domain "mydomain.com" via the <i>Email Domain</i> setting in the portal (Settings > Tenant Settings > Email Domain).</p>
Template body	Formatted text	<p>The body of the email to be sent.</p> <p>Includes three views:</p> <ul style="list-style-type: none"> • Design: WYSIWYG view of content. Enter and format body text here. • HTML: The same content in HTML format. Can also be edited if necessary and changes will be reflected in Design and Preview. • Preview: What the recipient sees. Read only - switch to Design view to make changes. <p>Dynamic content tags</p> <p>Tags can be used in the body, which are place holders in curly braces. These are replaced with actual request values when emails are sent.</p> <p>The following tags are available:</p> <ul style="list-style-type: none"> • {UserFullName} Name of requesting user • {UserEmail} Email address of requesting user • {UserPhone} Phone number of requesting user • {UserReason} Reason the requesting user gave • {DenyReason} Admin's reason for denial (only used for denial with reason) • {ComputerName} Name of requesting computer • {AdminUserName} Name of administrator receiving notification (only for admin notify)

Setting	Type	Description
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

TICKETING SYSTEM tab

You can set up an email notification to your ticketing system and embed the tags below for dynamic content.

Setting	Type	Description
Ticket system email	Text	The email address to which emails intended for your ticket system will be sent. For example: itsupport@mycompany.com
Email sender	Text Default: Admin By Request Team	The email address to be used as the sender for the email. Can be used with custom domains. Use the Email address button to set up custom domains.
Email subject	Text Default: Admin By Request	Text that will appear in the subject line of emails.
Get default	Button	Loads the default <i>Email template</i> for the option selected. NOTE: <ul style="list-style-type: none"> Default email templates are created by Admin By Request. Contact us if you wish to customize a default email template. Using this button will overwrite any customization you might have done in the <i>Template body</i>.
Email address	Button	Switches to Email Domain in Tenant Settings in the portal, allowing you to use a custom domain as the sender. This allows sending email from domains other than @adminbyrequest.com. NOTE: This is optional, but you cannot add an email sender field of e.g. "tom@mydomain.com" <i>unless</i> you have first set up the custom email domain "mydomain.com" via the <i>Email Domain</i> setting in the portal (Settings > Tenant Settings > Email Domain).
Template body	Formatted text	The body of the email to be sent to the ticketing system. Includes three views:

Setting	Type	Description
		<ul style="list-style-type: none"> • Design: WYSIWYG view of content. Enter and format body text here. • HTML: The same content in HTML format. Can also be edited if necessary and changes will be reflected in Design and Preview. • Preview: What the recipient sees. Read only - switch to Design view to make changes. <p>Dynamic content tags</p> <p>Tags can be used in the body, which are place holders in curly braces. These are replaced with actual request values when emails are sent.</p> <p>The following tags are available:</p> <ul style="list-style-type: none"> • {ID} Unique auditlog trace no • {APIID} ID for looking up this entry through the public Auditlog API • {Status} Requested, Approved, Denied, Started, Finished • {UserFullName} Name of the requesting user • {UserEmail} Email address of requesting user • {UserPhone} Phone number of requesting user • {UserReason} Reason the requesting user gave • {DenyReason} Admin's reason for denial • {ComputerName} Name of requesting computer • {AdminUserName} Admin approving or denying request • {InstallList} Installed programs • {UninstallList} Uninstalled programs • {AuditlogURL} URL to this entry in the auditlog • {RequestURL} URL to this entry in requests <p>Ticket ID</p> <p>You can find a ticket by its ticket ID using the Search button in the Auditlog.</p> <p>Voided text</p> <p>If a line has one or more tags and all tags in the line are empty, the entire line is automatically removed.</p>

Remote Access notification events

Setting	Type	Description
User requests approval	Toggle On Off Default: On	On - Sends a notification for <i>User requests approval</i> . Off - Does not send a notification.
Admin approves user request	Toggle On Off Default: On	On - Sends a notification for <i>Admin approves user request</i> . Off - Does not send a notification.
Admin denies user request	Toggle On Off Default: Off	On - Sends a notification for <i>Admin denies user request</i> . Off - Does not send a notification.
User starts remote session	Toggle On Off Default: Off	On - Sends a notification for <i>User starts remote session</i> . Off - Does not send a notification.
User finishes remote session	Toggle On Off Default: Off	On - Sends a notification for <i>User finishes remote session</i> . Off - Does not send a notification.
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

Sub Settings

Portal menu: **SRA > Settings > Remote Support Sub Settings**

Sub settings will *override* the global settings for the users or computers to which they apply. Both users and computers can be in Active Directory groups or organizational units.

If a user or computer hits multiple sub settings, the first in listed order *that includes the setting concerned* wins.

Overruling a global setting

As with sub-settings for EPM servers and workstations, SRA sub-settings mirror their respective global settings, with the addition of an **Override global settings** switch.

The following table lists the settings and sub-settings structure for both Unattended Access and Remote Support:

Unattended Access	Remote Support
Authorization	Authorization
Settings	Endpoint
Security	Settings

Unattended Access	Remote Support
Gateways	Security
Emails	Emails

Each of these can be on or off, which is controlled by a *Global Settings Override*:

Setting	Type	Description
Override global settings	Toggle On Off Default: On	<p>On - This setting will override its associated global setting. The global setting fields are then undimmed and become available for editing.</p> <p>Off - This setting will not override its associated global setting. The global setting fields remain dimmed.</p>

Scope for sub-settings

The key to sub-settings is to define and activate their **Scope**.

In the portal sub-settings, Scope is the second-top menu item, immediately below the **< Back** button.

Setting	Type	Description
Active	Toggle On Off Default: Off	<p>On - Sub-settings are active for the set named in <i>Sub settings name</i>.</p> <p>Off - Sub-settings are not active for the set named in <i>Sub settings name</i>.</p>
Sub settings name	Text	The name assigned to this set of sub-settings.
Portal user in group	Text	A list of groups into which users are placed, with multiple groups on separate lines.
Computer in group	Text	A list of groups into which computers are placed, with multiple groups on separate lines.
Computer in OU	Text	A list of organizational units into which computers are placed, with multiple OUs on separate lines.
Network scope	Toggle On Off One entry for each Gateway Default: Off	<p>On - Scope is active for this gateway.</p> <p>Off - Scope is not active for this gateway.</p> <p>Network scope means that these sub settings only apply to the selected gateway combination. A gateway represents an on-premise LAN - if no toggles are on, there is no network scope.</p>
Save	Button	Saves customization and changes to any fields. Note that reloading any defaults does not take effect until Save is clicked.

About sub-settings scope

Note the following:

- *Tiering* can be achieved by setting up a gateway on each tier and set portal user and sub settings network scopes.
- Computer scope does not work for discovered devices, because the server endpoint software is required to collect groups and OUs.
- Entra ID / Azure AD groups require you to set up the Entra ID Connector.
- All scopes must be met. If multiple user groups and computer Organizational Units (OUs) are specified, the user must be member of at least one of the groups and the computer in one of the OU locations.

In the portal text fields, multiple groups or OUs (Organizational Units) must be specified on separate lines. OUs can be specified as either:

- The bottom name, e.g. **Sales**. Any OU named Sales will match.
- Path from root using backslashes, e.g. **\US\Florida\Sales**.
- The fully distinguished name, e.g. **C=US,ST=Florida,OU=Sales**.

Document History

Document	Product	Changes
1.0 6 September 2024	26 August 2024	Initial document release.
1.1 4 October 2024	26 August 2024	Adjusted api URLs in <i>Prerequisites</i> section of chapter "Overview" so they point to the correct data center locations.

Index

A

AUTHORIZATION
Tab17

B

Basic Settings12

E

Emails20
Enable session recording13
End user initiated2
Endpoint (Menu)18
Enroll
Button6

G

Getting Started7

I

ICON
Tab18
IT admin initiated2

L

License3
Licensing5

M

MFA
Tab19

N

NOTIFICATION
Tab17

O

Overruling a global setting24

P

Pick computers
Button6
Platform Scope4
Prerequisites
Remote Support1
Product Enrollment3

R

RECORDING
Tab18
Remote Support1
Global Settings17
Remove
Button6
REQUEST EMAILS
Tab20
Require MFA14

S

Scope (sub-settings)25

Security 19

SESSION EXPIRY

 Tab20

Set session expiry15

Settings (Menu)18

Specify View Only15

Sub-Settings24

T

Test Drive 5

 Scope by computer groups 5

 Scope by manual selection5

TICKETING SYSTEM

 Tab 22

V

VIEW

 Tab19